

Configuration setup (Salto)

- First we need to edit CertificatePath, to the path, where is locksystem_hoteltime.pfx located. Add the complete path to the certificate with certificate name and ending .pfx. If you are using your own certificate, add the path to them. Also edit the CertificatePassword if you use a different one in your own certificate
- Change HostAddress to address of your locksystem server
- Add RemoteEndpoint address
- Open IntefaceManager.exe.config and edit httpEndPoint IP address to 0.0.0.0 and port, which is provided by hoteltime support in section modules. You can use your own port, but let Hoteltime support know which you are using, they must set it up in hoteltime settings
- Verify Port with the supplier of the encoder
- If you are using only one encoder, you can delete Coder section if not:
 - Edit CoderIDs in Coders section and the default one according to settings in locksystem server
 - To add more coders, in the section Coders copy whole Coder section and paste under the first one
 - The RemoteEndpoint value should be the address of the computer to which the coder is connected. See table below.

```
<?xml version="1.0" encoding="utf-8" ?>
<SaltoSettings>
  <HostAddress>127.0.0.1</HostAddress>
  <Port>8888</Port>
  <CoderID>1</CoderID>
  <RoomCodeDelimiter>/</RoomCodeDelimiter>
  <WriteRoomCodeOnTrack3>false</WriteRoomCodeOnTrack3>
  <Coders>
    <Coder>
      <CoderID>01</CoderID>
      <RemoteEndpoint></RemoteEndpoint>
    </Coder>
  </Coders>
  <Demo>false</Demo>
  <LoggingLevel>5</LoggingLevel>
  <Mobile>false</Mobile>
  <Prefix>+420</Prefix>
  <CertificatePath></CertificatePath>
  <CertificatePassword>hoteltime</CertificatePassword>
  <UseSecure>true</UseSecure>
</SaltoSettings>
```

| | Description | Mandatory | Default Value |
|----------------------|---|-----------|---------------|
| HostAddress | address of the locksystem and must be provided by the supplier or local IT | yes | 127.0.0.1 |
| Port | port of the Lock System to which we should send requests | yes | 8888 |
| CoderID | Encoder ID according to the lock system settings - this is the default ID, so if no other will work, use this | yes | 1 |
| RoomCodeDelimiter | can be used when changing the name of the room | yes | / |
| WriteRoomCodeOnTrack | | yes | false |
| RemoteEndpoint | IP address of the reception computer from which it is coded to CoderID | yes | 127.0.0.1 |
| Demo | Used only to test the connection between the browser and the IFC | yes | false |
| LoggingLevel | Allows you to see more info about the application in the log | yes | 5 |
| Mobile | | yes | false |
| Prefix | Indicates prefix of mobile | yes | +420 |
| CertificatePath | indicates where the certificate is located | yes | |
| CertificatePassword | specifies which password will be used when installing certificates | yes | hoteltime |
| UseScure | serves for secure communication via the Internet between the local web browser and the ifc manager | yes | true |




Diagram which describes how locksystem works